

# Configuring Artifactory

## Overview

You can access the General Configuration settings of Artifactory in the **Admin** tab under **Configuration | General Configuration**.

### Saving changes


Any changes you make must be saved in order for them to take effect.


## General Settings


The fields under General Settings allow you to set up various global parameters in Artifactory. The ? icon next to each field provides a detailed description of the field. Fields marked with a red star are mandatory.

### General Configuration


#### General Settings


Server Name 

Custom URL Base 

File Upload Max Size \* 

Bintray Max Files Upload \*

Date Format \* 

Global Offline Mode 

Enable Help Component


### Page Contents


- [Overview](#)
- [General Settings](#)
- [Global Replication Blocking](#)
- [Folder Download Settings](#)
- [Trash Can Settings](#)
- [Look and Feel Settings \(Branding\)](#)
- [Custom Message](#)
- [Direct Cloud Storage Download Settings](#)

### Read More

- [Configuring the Database](#)
- [Configuring the Filestore](#)
- [Checksum-Based Storage](#)
- [Direct Cloud Storage Download](#)
- [Configuring Repositories](#)
- [Configuring Security](#)
- [Configuring a Reverse Proxy](#)
- [Mail Server Configuration](#)
- [IPv6 Support](#)
- [Configuration Files](#)
- [YAML Configuration File](#)
- [Exposing Maven Indexes](#)
- [Clustering Artifactory](#)


The General Settings fields are as follows:

Server Name (mandatory)	The name of the server to be displayed on the title of each page.
Custom URL Base	<p>By default, URLs generated in Artifactory use the context URL returned by your servlet container as a base. A custom URL base is useful when Artifactory is running behind a proxy. In this case the base for URLs generated in Artifactory for links and redirect responses must be specified manually.</p> <p>Another reason to change the base URL would be to have non-request-based operations in Artifactory use the correct address, for example in generated emails.</p> <p>This may also be modified using the <a href="#">Update Custom URL Base</a> REST API.</p> <div><p> <b>Overriding the Custom URL Base</b></p><p>You can override the Custom URL Base by adding an <code>X-Artifactory-Override-Base-Url</code> HTTP header to your request. This can be useful if you need Artifactory to answer to more than one host name.</p></div>

File Upload Max Size	Maximum size allowed for files uploaded via the web interface.
Bintray Max Files Upload	The maximum number of files that can be <a href="#">pushed to Bintray</a> in a single operation.
Date Format (mandatory)	The date format for displaying dates in the web interface.
Global Offline Mode	When checked, Artifactory will behave as if it is not connected to an external network (such as the internet), and therefore, will not query remote repositories (regardless of the offline status of any specific remote repository).
Enable Help Component	<p>If set, Artifactory will display context sensitive help topics in the top right corner of the UI.</p> 

## Global Replication Blocking

By configuring Global Replication Blocking, you can enable or disable replication globally as needed.



Block Replications	When set, push and pull replication will be blocked according to the check boxes below, regardless of the configuration for specific repositories.
Block Push Replications	When set, push replication will be blocked regardless of the configuration for specific repositories.
Block Pull Replications	When set, pull replication will be blocked regardless of the configuration for specific repositories.

## Folder Download Settings

### Folder Download Settings

Enable Folder Download

Max Size [?](#)

Max Number of Files [?](#)

Max Parallel Folder Downloads [?](#)


Enable Folder Download	Must be set to enable folder download
Max Size	The maximum size (in MB) of a folder that may be downloaded
Max Number of Files	The maximum number artifacts that may be downloaded under one folder
Max Parallel Folder Downloads	The maximum number of folder download requests that may be run concurrently

## Trash Can Settings

### Trash Can Settings

Enable Trash Can

Retention Period (Days) [?](#)

 [Empty Trashcan](#)

Enable Trash Can	If set, trash can will be enabled and deleted items will be stored in the trash can for the specified retention period.
Retention Period	The number of days to keep deleted items in the trash can before deleting permanently.
Empty Trash Can	Click to delete all items currently in the trash can permanently.

## Look and Feel Settings (Branding)

In the Look and Feel Settings you can configure Artifactory to present your company logo in the top left corner of the screen and customize the footer text.

You may either upload an image to be used locally, or reference a remote image URL.

## Look and Feel Settings


Upload from: **File** Url

Logo File

Drop file here or **Select File**

**Clear**

**artifactory** By JFrog

<b>File</b>	If selected, upload your company logo image file. <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"><p> <b>Logo file upload</b> The uploaded logo file is copied into the <code>ARTIFACTORY_HOME/etc/ui</code> folder.</p></div>
<b>URL</b>	If selected, specify the URL from which Artifactory should display your company logo

## Custom Message

You can display a **Custom Message** at the top of Artifactory screens.

**JFrog Artifactory**QWelcome, Admin ( Log Out )Help

**Upgrade Notice:** We have upgraded to Artifactory 4. Make sure all your repositories are [single package type](#).

To configure the custom message, in the **Admin** module, select **Configuration | General**.

### Custom Message

Enabled

Show Only in Home Page

Title

Upgrade Notice

Title Color

#43A047


Message

```
We have upgraded to Artifactory 4. Make sure all your repositories are  
[http://www.jfrog.com/confluence/display/RTF/Upgrading+Artifactory#UpgradingArtifactory-SinglePackageTypeRepositories,single package type].
```

 To embed a link inside the message use : [http://example.com, text]


Enabled	Toggles the custom message on and off.
Show Only in Home Page	When set, the custom message will only be displayed on the Artifactory <a href="#">Home Page</a> .
Title	The title for the message.
Title Color	Click on the colored rectangle to select a color, or enter the color in Hex format.
Message	The message to display. You can include links in the message using the following format: [<link URL>, <link text>]

### Direct Cloud Storage Download Settings



## General Configuration

#### Direct Cloud Storage Download Settings

Minimum Direct Cloud Storage Download Size (MB) \* 

Minimum Direct Cloud Storage Download Size	The minimum size of an artifact for which when requested, Artifactory will redirect the request for direct download from cloud storage.
--	---

