


Updating Your Profile

Overview

Your profile page is used to manage the following aspects of your user profile:

- [API Key](#)
- [Password](#)
- [Email](#)
- [Bintray Settings](#)
- [Binding OAuth Accounts](#)

To display your profile page, click your login name on the top right-hand corner of the screen.



Unlocking Your Profile

To edit your profile, you first need to unlock it by entering your current password and clicking **Unlock**.

Once unlocked, you can modify all the elements of your user profile.

Page Contents

- [Overview](#)
- [Unlocking Your Profile](#)
- [Changing your Personal Settings](#)
 - [API Key](#)
 - [Revoking or Regenerating an API Key](#)
 - [REST API](#)
 - [Changing Your Password and Email](#)
 - [Password Reminder](#)
- [Bintray Settings](#)
- [SSH Key](#)
- [Binding OAuth Accounts](#)



Saving your changes

Be sure to click **Update** to save any changes to your profile.



Using external authentication

If you are using an external authentication server (such as [HTTP SSO](#), [OAuth SSO](#), or [SAML SSO](#)), you can ask your administrator to give you access to your [API key](#), [Bintray credentials](#) and [SSH public key](#) without having to unlock your profile.

Changing your Personal Settings

Personal settings include your Artifactory API Key, password and email address.



You are not able to change your password if Artifactory is configured to use external authentication such as LDAP.

API Key

Artifactory allows authentication for REST API calls using your API key as an alternative to your username and password in two ways: you may either using the `X-Jfrog-Art-API` header with which you can specify an API key , or you may use basic authentication using your username and API key (instead of your password). For more details, please refer to the [REST API documentation](#).

Artifactory version

To use your API key for authentication, it must be generated using Artifactory 4.4.3 or later. If generate before, you **must** regenerate your API key and use the new key as a password for basic authentication.

Creating an API Key

To create an API Key, once you have unlocked your profile, click the "Generate" button next to the **API Key** field.




Revoking or Regenerating an API Key

Once an API Key is created, it displayed, masked, in the corresponding field. Click the "View" icon to see the API Key in clear-text, or the "Copy" icon to copy the API Key to the clipboard.

To revoke the current API Key, click "Revoke API Key" Note that any REST API calls using the current API key for authentication will no longer be valid.

You may revoke the current API Key and create a new one in a single action by clicking "Regenerate". Any REST API calls using the current API key for authentication will no longer be valid, until you replace the API Key with the new one you just generated.



REST API

The following REST API endpoints are available with regard to API Keys:

Endpoint	Description
Create API Key	Create an API key for the current user.
Get API Key	Get the current user's own API key.
Revoke API Key	Revokes the current user's API key.
Revoke User API Key	Revokes the API key of another user (requires Admin privileges).
Revoke All API Keys	Revokes all API keys currently defined in the system (requires Admin privileges).

Changing Your Password and Email


Once your profile is unlocked, Artifactory displays your password in an encrypted format that can be used whenever you need to provide your password in an environment that is not secure. For example, when making REST API calls over HTTP.

The encrypted password is initially masked, but you may click the "View" icon to view the encrypted password in clear-text. You may also click the "Copy" icon to copy the encrypted password to the clipboard.

To change your Artifactory password, enter your new password and verify it.


You can also modify your email address.

Personal Settings



The Personal Settings form contains three input fields: 'New Password', 'Retype Password', and 'Email Address *'. To the right of the 'New Password' field is a 'Password Strength' indicator bar. The entire form is enclosed in a red rectangular border.

Authentication Settings




The Authentication Settings form includes an 'API Key' field with a redacted value, an eye icon, a copy icon, and a settings gear icon. Below it is a 'Revoke API Key' button with a red 'X' icon. The 'Encrypted Password' field, also with a redacted value, eye icon, and copy icon, is highlighted with a red rectangular border.



For more information about using secured passwords with your profile, please refer to [Centrally Secure Passwords](#).

Password Reminder

If you forget your password, on the Artifactory Login dialog, select **Forgot Password**, and enter your username in the following dialog that is displayed.



Two dialog boxes are shown. The first is the 'Welcome to JFrog Artifactory!' login dialog with fields for 'Username*' and 'Password*', a 'Remember me' checkbox, a 'Log In' button, and a 'Forgot Password?' button highlighted with a red border. The second is the 'Forgot Password' dialog with a 'Username*' field and a 'Submit' button.

When you click **Submit**, Artifactory will send a message to the email address configured for your user account, with a link you can click on to reset your password.

Bintray Settings

Bintray is JFrog's platform to store and distribute your software libraries. For more details please refer to the [JFrog Bintray Page](#).

Upon installation, Artifactory has Bintray's JCenter Java repository defined as a remote repository.

You may freely read from JCenter, and other Bintray repositories, however to upload an artifact, or perform other operations on Bintray through Artifactory such as search, you must have a Bintray account and provide your credentials through your profile page.

To provide your Bintray credentials, enter your **Bintray Username** and the **Bintray API Key** you received when registering to Bintray into the specified fields in Artifactory.

To verify that your credentials are valid you can click **Test**.

Bintray Settings

Bintray Username

Bintray API Key



[Register to Bintray...](#)

Test

SSH Key

From version 4.4, Artifactory supports authentication via SSH for the [Git LFS](#) client and the [Artifactory CLI](#).

To be authenticated via SSH, you need to enter your SSH public key in the **SSH Public Key (RSA)** field.

SSH

SSH Public Key (RSA)

```
Starts with 'ssh-rsa', 'ssh-dss', 'ssh-ed25519', 'ecdsa-sha2-nistp256', 'ecdsa-sha2-nistp384', or 'ecdsa-sha2-nistp521'
```

Binding OAuth Accounts

From version 4.2, Artifactory is integrated with OAuth allowing you to log in through your account with one of the configured OAuth providers. To do so, you need to bind your OAuth account to your Artifactory user by clicking **Click to bind** next to the corresponding OAuth provider. For more details, please refer to [OAuth Integration](#).

OAuth User Binding



Git Enterprise

[Click to bind](#)



Google-JFrog

[Click to bind](#)



OpenID

[Click to bind](#)
